\$9.95

DATA HANDLING MANUAL

BUSINESS

- Exchange data between PC's. Macintosh and Apple II's.
- Create secure back-ups.
- Transfer text.
 - Lotus 123 Excel
 - Framework
 Pagemaker and many more.



Complete utility programs in data strip format are contained in the back of this book.

Copyright © 1986 by Cauzin Systems, Inc. All rights reserved.

Apple is a registered trademark and Applesoft, AppleWorks, Apple Writer, ImageWriter, MacWrite, ProDOS, and Super Serial Card are trademarks of Apple Computer, Inc.

Cauzin and SOFTSTRIP are registered trademarks and STRIPPER is a trademark of Cauzin Systems, Inc.

dBASE is a registered trademark and Framework and MultiMate are trademarks of Ashton-Tate.

Dumpling is a trademark of Microtek, Inc.

Epson is a registered trademark of Epson America, Inc.

Grappler is a trademark of Orange Micro, Inc.

IBM is a registered trademark of International Business Corporation, Inc.

Lotus and 1.2.3 are registered trademarks of Lotus Development Corporation.

Macintosh is a trademark of McIntosh Laboratories, and is licensed to Apple Computer, Inc.

Microsoft is a registered trademark, MS is a trademark, and Excel is a product of Microsoft Corporation.

PageMaker is a registered trademark of Aldus Corporation.

ReadySetGo is a trademark of Manhattan Graphics Corporation.


Sidekick is a trademark of Borland International.

ThinkTank is a trademark of Living VideoText, Inc.

Turbo Pascal is a registered trademark of Borland International.

WordStar is a registered trademark of MicroPro International Corporation.

SOFTSTRIP® Data Handling Manual Series 1



Your complete guide for:

Creating Secure Documents

Transferring Data Between Programs

Backing-Up Data for Filing

Distributing Data Between Locations

Introducing...

The SOFTSTRIP Advantage

- Send your proposal from Framework or Word-Star on an IBM to PageMaker on a Macintosh for top-quality printing in company publications.
- Write a committee report with AppleWorks on your Apple II at home and print it out with your IBM PC and letter-quality printer at the office.
- Develop a budget with Excel on your Macintosh and distribute it by inter-office mail to all the Macintosh and IBM PC users in the company.
- Back-up your information on data strips that can be filed along with the original documents.

At the heart of these procedures is the SOFTSTRIP System and Cauzin's STRIPPER programs. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Data transfer is actually not a very new idea. It's been going on for years, and you may already be deeply involved in it through telecommunications. If you have several serial cards and modems, your personal collection of expensive cables, a couple of communications programs, and shares in AT&T, file transfers are a breeze

The SOFTSTRIP System allows you to transfer data between different computers at a fraction of the cost and bother of telecommunications. At the same time, your sensitive data is protected from sight by encoding as data strips.

More applications are being developed all the time. Perhaps you have a unique situation that we can help with. If you have suggestions or information for future titles, contact us.

PLD and KJL for Cauzin Systems

TABLE OF CONTENTS

		Page
General	! Use	
	Confidential Memo	6
Word P	Processing Transfer	
	Apple Writer and WordStar	8
	AppleWorks and WordStar	10
	MacWrite and WordStar	12
	Apple Writer and MacWrite	14
	AppleWorks and MacWrite	16
	MultiMate and MacWrite	18
	MultiMate and AppleWorks	20
	MultiMate and Apple Writer	22
	IBM ThinkTank and Mac ThinkTank	24
	IBM ThinkTank and Apple ThinkTank	26
	Mac ThinkTank and Apple ThinkTank	28
	IBM MS-Word and AppleWorks	30
	IBM MS-Word and Apple Writer	32
	IBM MS-Word and MacWrite	34
Spreads	heet Transfer	
	Lotus 1•2•3 and Excel	36
	Lotus 1•2•3 and AppleWorks	38
Data Bo	ase Transfer	
	AppleWorks and dBASE	40
Source	Code Transfer	
	Turbo Pascal and Macintosh Pascal	42
	IBM BASIC and Applesoft BASIC	44
	IBM BASIC and Macintosh BASIC	46
Desktop	Publishing Transfer	
	Framework to PageMaker	48
	Lotus 1•2•3 to PageMaker	50
	WordStar to PageMaker	52
	IBM MS-Word to PageMaker	54
	MultiMate to PageMaker	56
	AppleWorks to PageMaker	58
	Apple Writer to PageMaker	60
	Framework to ReadySetGo	62
	Lotus 1•2•3 to ReadySetGo	64
	WordStar to ReadySetGo	66
	IBM MS-Word to ReadySetGo	68
	MultiMate to ReadySetGo	70
	AppleWorks to ReadySetGo	72
	Apple Writer to ReadySetGo	74
The Ca	uzin Converters	
2110 04	How to Use Them	76
	For the Macintosh	77
	For the IBM PC	78
	For the Apple II	79
	For Lotus and Excel	80
	TOLLOUIS AND LACEL	00

Ready...

...Set...

...Strip

All the enclosed Application Notes detail the procedures for using SOFTSTRIP data strips with popular application programs.

Most of the titles in this series transfer ASCII text files between applications. We explain each step involved and the commands to use.

Since these use simple ASCII files, you may not be able to transfer all the formatting used by a word processor. This is especially true where the format is stored in a way that is supported by only one of the applications you are using. Your text will transfer, but indenting may not.

What You'll Need

Each Note has a complete list of System Requirements. Be sure you have the right equipment before trying a particular data transfer.

We presume a working knowledge of the two applications between which you are moving data. The Note tells you the most important commands to use, but it cannot take the place of experience with the programs.

Also, we trust that you have some experience with Cauzin's STRIPPER programs for dot matrix printers. These are available for IBM PC, Macintosh, and Apple II computers with Epson or ImageWriter printers. You need STRIPPER for each machine that will be originating data.

Finally, you should know how to operate the SOFTSTRIP System reader. The reader comes with an Accessory Kit for IBM PC, Macintosh, or Apple II. Extra kits are available from your dealer. You need only one reader, and a kit for each computer that will receive data.

The Cauzin Converters

Even though any computer can read any strip, WordStar still does not know what to do with a MacWrite document. They store information in different formats.

For example, Apple DOS 3.3 stores text files with the high bit set for each ASCII character. However, WordStar and MacWrite do not use this technique. If you read a set of data strips from DOS 3.3 Apple Writer into MacWrite on a Macintosh, the result is a screen full of gibberish.

We provide you with all the utilities you need to complete the data transfer. They are printed in data strip form at the end of this manual. There is one set of strips for each of the machines. Read the data strips into the appropriate machine and the utilities will be stored on your data disk.

All the utilities you need are printed at the back of this manual.

Run the IBM PC utilities by entering the filename from DOS. Thus, you run the IBM to Apple ProDOS program by entering:

IBM2PDOS

The program will prompt you for the filename you are starting with and the name you want for the new file. If the utility has a .BAS extension, you need to RUN it from BASIC or BASICA.

For the Macintosh utility, just double click on the Convert icon to run the program. The two Apple utilities are compatible with DOS 3.3 and ProDOS.

CONFIDENTIAL **MEMO**

IBM PC Computers and 100% Compatibles

Encode Your Data Strips for Extra Security When Distributing Sensitive Data



This Note details a procedure for encoding and decoding sensitive files on an IBM PC or 100% compatible.

Once the files are encoded, they are printed in data strip format. This adds another level of security and provides an easy way to distribute documents.

At the heart of the procedure is the Softstrip® System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- STRIPPER™ for the IBM
- Epson[®] RX or FX printer
 Printer interface card

√ Cauzin Softstrip® Reader:

• IBM PC Accessory Kit

Encoding

- V Create a text file with your IBM word processor
- Run CIPHER on the file

 - Select the Encode function
 The Code Key is a word, phrase, or sentence of less than 256 characters
- **V** Print strips of the encoded file with IBM STRIPPER Check printer ribbon and paper supply.
- Photo-copy and distribute the data strips

Decoding

- $\sqrt{\text{Read strips into your IBM PC}}$ or 100% compatible
- √ Run CIPHER on the file
 - Select the Decode function
 - · Enter the same Code Key as used for for encoding.
 - Be careful of upper- and lower-case letters.
 - Use of the wrong Key will: -produce incorrect results or
 - -bomb the program
- √ Open the file with your IBM word processor

Other Application Notes show how to transfer text files into word processors on other computers.

APPLE WRITER to WORDSTAR WORDSTAR to APPLE WRITER

Exchanging Computer Data Using Cauzin Softstrip[®] Data Strips



This Note details the procedure for exchanging text files between Apple Writer on an Apple II and WordStar on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but an IBM file uses straight ASCII. Also, IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return.

SYSTEM REQUIREMENTS

√ Apple[®] II computer:

- Apple WriterTM II (DOS 3.3 or ProDOSTM)
- STRIPPER™ for the Apple II
- Epson[®] RX or FX; or ImageWriter[™] I or II
- Dumpling[™], Grappler[™], or Super Serial Card™ (built into Apple //c)

√ IBM[®] PC or 100% compatible: • WordStar[®] (except WordStar 2000)

- · STRIPPER for the IBM
- · Epson RX or FX printer
- · Printer interface card

- · Apple II Accessory Kit
- IBM PC Accessory Kit

To: Apple Writer From: WordStar

- √ Create a file with WordStar
- √ Run BLUE2RED on the file
 This converts a file to Apple format.
- √ Print strips of the text file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Apple II

 Press D for DOS 3.3 or P for ProDOS depending on your Apple Writer.
- √ Load into Apple Writer


To: WordStar

From: Apple Writer

- √ For ProDOS Apple Writer
 Use your ProDOS System Master to convert your files to DOS 3.3.
- √ For DOS 3.3 Apple Writer Save files as usual.
- √ Print strips of the text file with Apple STRIPPER
- √ Read strips into IBM PC
 Filenames are automatically edited to match IBM requirements.
- √ Run RED2BLUE on the file
- ✓ Open the file in WordStar:
 Turn off hyphenation (CONTROL -O.H.)
 - Turn off hyphenation (CONTROL-O,H)
 Use CONTROL-Q, CONTROL-Q, CONTROL-B to format the text.

APPLEWORKS to WORDSTAR WORDSTAR to APPLEWORKS

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between AppleWorks on an Apple II and WordStar on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but an IBM file uses straight ASCII. Also, IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return.

SYSTEM REQUIREMENTS

√ Apple® II computer:

AppleWorksTM

• STRIPPERTM for the Apple II

Epson[®] RX or FX; or ImageWriter[™] I or II

• DumplingTM, GrapplerTM, or Super Serial Card™ (built into Apple //c)

√ IBM[®] PC or 100% compatible: • WordStar[®] (except WordStar 2000)

· STRIPPER for the IBM

· Epson RX or FX printer

· Printer interface card

√ Cauzin Softstrip® Reader:

Apple II Accessory Kit

· IBM PC Accessory Kit

To: AppleWorks From: WordStar

- √ Create a file with WordStar
- √ Run BLUE2RED on the file This converts a file to Apple format.
- √ Print strips of the text file with IBM STRIPPER Check printer ribbon and paper supply.
- √ Read strips into Apple II Press P for the ProDOS version of the Cauzin communications program.
- **√** Load into AppleWorks Open a Word Processing file from the text (ASCII) file

To: WordStar From: AppleWorks

- $\sqrt{}$ For a word processing file Print to a text (ASCII) file on disk.
- √ For a spreadsheet or data base
 - Open-Apple-P
 - Select data, set format as prompted · Open-Apple-P, Print to the Clipboard
 - Open Word Processing file from Scratch
 - · Open-Apple-M, Move from Clipboard

 - Edit the text if necessaryPrint to a text (ASCII) file on disk
- √ Convert the text file to DOS 3.3 Use your ProDOS System Master.
- √ Print strips of the text file with Apple STRIPPER
- √ Read strips into IBM PC Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- √ Open the file in WordStar:
 - Turn off hyphenation (CONTROL-O,H)
 - Use CONTROL-Q, CONTROL-Q, CONTROL-B to format the text.

MacWRITE to WORDSTAR WORDSTAR to MacWRITE

Exchanging Computer Data Using Cauzin Softstrip[®] Data Strips



This Note details the procedure for exchanging text files between MacWrite on an Apple Macintosh and WordStar on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. IBM files use a carriage return and a line feed to end each line, while Macintosh uses just a carriage return.

SYSTEM REQUIREMENTS

- √ MacintoshTM computer (any model):
 - MacWrite™
 - STRIPPER™ for the Macintosh
 - ImageWriterTM I or II

- √ IBM[®] PC or 100% compatible: WordStar[®] (except WordStar 2000)
 - · STRIPPER for the IBM
 - Epson® RX or FX printer
 - · Printer interface card

- Macintosh Accessory Kit
- (CauzComm 1.6 or higher) · IBM PC Accessory Kit

To: MacWrite

From: WordStar


- √ Create a file with WordStar
- √ Run IBM2MAC on the file
 This converts a file to Macintosh format.
- √ Print strips of the converted text file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Open the file from MacWrite Let carriage returns mark Paragraphs.

To: WordStar From: MacWrite

- √ Create a text file with MacWrite
 - Save the file as Text Only
 - Let carriage returns mark Paragraphs
- √ Print strips of the text file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
 This converts a file to IBM format.
- √ Open the file in WordStar
 Turn off hyphenation (CONTROL-O,H)
 - Use CONTROL-Q, CONTROL-Q, CONTROL-B to format the text.

APPLE WRITER to MacWRITE MacWRITE to APPLE WRITER

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between Apple Writer on an Apple II and MacWrite on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but MacWrite uses straight ASCII characters.

SYSTEM REQUIREMENTS

√ MacintoshTM computer:

- MacWriteTM
- STRIPPERTM for the Macintosh
- ImageWriterTM I or II

√ Apple® II computer:

- Apple Writer[™] (DOS 3.3 or ProDOS)
- ProDOS™ System Master
- STRIPPER™ for the Apple II
- Epson® RX or FX; or ImageWriter I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- · Apple II Accessory Kit

To: MacWrite From: Apple Writer

- √ For ProDOS Apple Writer
 Use your ProDOS System Master to convert your files to DOS 3.3
- √ For DOS 3.3 Apple Writer Save files as usual.
- √ Print strips of the text file with Apple STRIPPER
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 Select Text from File Conversion
- √ Run CONVERT on the file
 This converts a file to Macintosh format.
- √ Load into MacWrite

 Let carriage returns mark Paragraphs.

To: Apple Writer From: MacWrite

- √ Create a text file with MacWrite
 - · Save the file as Text Only
 - · Let carriage returns mark Paragraphs
- √ Print strips of the text file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into Apple II

 Press D for DOS 3.3 or P for ProDOS depending on your Apple Writer.
- √ Load into Apple Writer

APPLEWORKS to MacWRITE MacWRITE to APPLEWORKS

Exchanging
Computer Data
Using Cauzin
Softstrip®
Data Strips



This Note details the procedure for exchanging text files between AppleWorks on an Apple II and MacWrite on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but MacWrite uses straight ASCII characters.

SYSTEM REQUIREMENTS

√ Macintosh™ computer:

- MacWriteTM
- STRIPPER™ for the Macintosh
- ImageWriter $^{\text{TM}}$ I or II

√ Apple® II computer:

- AppleWorksTM
- ProDOS™ System Master
- STRIPPER™ for the Apple II
- Epson® RX or FX; or ImageWriter I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- · Apple II Accessory Kit

To: MacWrite From: AppleWorks

- $\sqrt{\text{For a word processing file}}$ Print to a text (ASCII) file on disk.
- $\sqrt{}$ For a spreadsheet or data base

· Open-Apple-P

- · Select data, set format as prompted · Open-Apple-P, Print to the Clipboard
- Open Word Processing file from Scratch · Open-Apple-M, Move from Clipboard


- Edit the text if necessaryPrint to a text (ASCII) file on disk
- $\sqrt{\text{Convert the text file to DOS 3.3}}$ Use your ProDOS System Master.
- $\sqrt{\text{Print strips of the converted text}}$ file with Apple STRIPPER
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Run CONVERT on the file This converts a file to Macintosh format.
- √ Load into MacWrite Let carriage returns mark Paragraphs.

To: AppleWorks From: MacWrite

- √ Create a text file with MacWrite
 - Save the file as Text Only
 - Let carriage returns mark Paragraphs
- $\sqrt{\text{Print strips of the text file with}}$ Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into Apple II Press P for the ProDOS version of the Cauzin communications program.
- √ Load into AppleWorks Open a Word Processing file from the text (ASCII) file.

MULTIMATE to MacWRITE MacWRITE to MULTIMATE

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between MultiMate on an IBM PC or 100% compatible and MacWrite on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. IBM files use a carriage return and a line feed to end each line, while Macintosh uses just a carriage return

SYSTEM REQUIREMENTS

- $\sqrt{\text{Macintosh}^{\text{TM}}}$ computer (any model):
 - MacWriteTM
 - STRIPPER™ for the Macintosh
 - ImageWriter™ I or II
- √ IBM® PC or 100% compatible:
 - MultiMateTM
 - STRIPPER for the IBM
 - · Epson RX or FX printer
 - · Printer interface card
 - √ Cauzin Softstrip® Reader:
 - Macintosh Accessory Kit (CauzComm 1.6 or higher)
 - IBM PC Accessory Kit

To: MacWrite From: MultiMate


- √ Create a file with MultiMate
- √ Convert MultiMate file to ASCII
 - Run FILECONV (MultiMate Utilities)
 - Select MultiMate to ASCII conversion
 - · Enter filenames as prompted
 - Use .TXT extension for new filename
 Press F10 to convert the file
- √ Run IBM2MAC on the .TXT file
- $\sqrt{\text{Print strips of the converted .TXT}}$ file with IBM STRIPPER Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Load into MacWrite Let carriage returns mark Paragraphs.

To: MultiMate From: MacWrite

- √ Create a text file with MacWrite
 - Save the file as Text Only
 - · Let carriage returns mark Paragraphs
- $\sqrt{\text{Print strips of the text file with}}$ Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into IBM PC Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- **√** Convert ASCII file to MultiMate
 - Run FILECONV (MultiMate Utilities) Select ASCII to MultiMate conversion
 - · Enter filenames as prompted
 - · Press F10 to convert the file
- **V** Open the file in MultiMate

APPLEWORKS to MULTIMATE MULTIMATE to APPLEWORKS

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between AppleWorks on an Apple II and MultiMate on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but an IBM file uses straight ASCII. Also, IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return.

SYSTEM REQUIREMENTS

√ Apple® II computer:

AppleWorksTM

• STRIPPERTM for the Apple II

• Epson® RX or FX; or ImageWriter™ I or II

 Dumpling™, Grappler™, or Super Serial Card™ (built into Apple //c)

√ IBM® PC or 100% compatible:

MultiMate™

- STRIPPER for the IBM
- · Epson RX or FX printer
- · Printer interface card

- · Apple II Accessory Kit
- IBM PC Accessory Kit

To: AppleWorks From: MultiMate

√ Convert MultiMate file to ASCII

- Run FILECONV (MultiMate Utilities)
- Select MultiMate to ASCII conversion
- Enter filenames as prompted
- Use .TXT extension for new filename
- Press F10 to convert the file
- √ Run BLUE2RED on the .TXT file
 This converts a file to Apple format.
- √ Print strips of the converted .TXT file with IBM STRIPPER
- √ Read strips into Apple II

 Use ProDOS version of the Cauzin communications program.
- √ Load into AppleWorks


 Open text file from the Word Processor.

To: MultiMate From: AppleWorks

- √ For a word processing file
 Print to a text (ASCII) file on disk.
- $\sqrt{\text{For a spreadsheet or data base}}$
 - · Open-Apple-P
 - · Select data, set format as prompted
 - · Open-Apple-P, Print to the Clipboard
 - Open Word Processing file from Scratch
 - · Open-Apple-M, Move from Clipboard
 - · Edit the text if necessary
 - · Print to a text (ASCII) file on disk
- √ Convert the text file to DOS 3.3 Use your ProDOS System Master.
- √ Print strips of the text file with Apple STRIPPER
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- √ Convert text file to MultiMate
 - Run FILECONV (MultiMate Utilities)
 - Select ASCII to MultiMate conversion
 - · Enter Filenames as prompted
 - Press F10 to convert the file

MULTIMATE to APPLE WRITER APPLE WRITER to MULTIMATE

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between MuliMate on an IBM PC or 100% compatible and Apple Writer on an Apple II.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return

SYSTEM REQUIREMENTS

√ Apple® II computer:

- Apple WriterTM
- ProDOS™ System Master
- STRIPPER $^{\text{TM}}$ for the Apple II
- Epson[®] RX or FX; or ImageWriter™ I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ IBM® PC or 100% compatible:

- MultiMate™
- STRIPPER for the IBM
- · Epson RX or FX printer
- · Printer interface card

- · Apple II Accessory Kit
- IBM PC Accessory Kit

To: Apple Writer From: MultiMate

- √ Create a file with MultiMate
- √ Convert MultiMate file to ASCII
 - Run FILECONV (MultiMate Utilities)
 - Select MultiMate to ASCII conversion
 - Enter filenames as prompted
 - Use .TXT extension for new filename
 - Press F10 to convert the file
- √ Run BLUE2RED on the .TXT file This converts a file to Apple format.
- √ Print strips of the converted .TXT file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Apple II


 Press D for DOS 3.3 or P for ProDOS depending on your Apple Writer.
- √ Load into Apple Writer

To: MultiMate From: Apple Writer

- √ For ProDOS Apple Writer
 Use your ProDOS System Master to convert your file to DOS 3.3.
- √ For DOS 3.3 Apple Writer Save file as usual.
- **V** Print strips of the text file with Apple STRIPPER
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- √ Convert text file to MultiMate
 - Run FILECONV (MultiMate Utilities)
 - Select ASCII to MultiMate conversion
 - Enter filenames as prompted
 - Press F10 to convert the file
- √ Open the file in MultiMate

Between IBM THINKTANK and MACINTOSH THINKTANK

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging outline files between ThinkTank on a Macintosh and ThinkTank on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. IBM files use a carriage return and a line feed to end each line, while Macintosh uses just a carriage return.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- ThinkTank™ for the IBM STRIPPER™ for the IBM Epson® RX or FX printer

- · Printer interface card

√ Macintosh™ computer:

- ThinkTank for the Macintosh
- STRIPPER for the Macintosh
- ImageWriter™ I or II

- IBM PC Accessory Kit
- Macintosh Accessory Kit (CauzComm 1.6 or higher)

To: Mac ThinkTank From: IBM

√ Save a ThinkTank outline as text

• Use the Port command


- Select Textfile, Send, and StructuredA .TXT file is written to your disk
- √ Run IBM2MAC on the .TXT file
 This converts a file to Macintosh format.
- √ Print strips of the converted .TXT file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Load the text file into ThinkTank Select Open from the File menu.

To: IBM ThinkTank From: Macintosh

- √ Save a ThinkTank outline Select Save from the File menu.
- √ Print strips of the outline file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
 Add a .TXT extension to the new file.
- √ Load the text file into ThinkTank
 - Use the Port command
 - Select Textfile and Receive
 - Select Word-wrapped and Standard

Between IBM THINKTANK and APPLE II THINKTANK

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging outline files between ThinkTank on an Apple II and ThinkTank on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Living Videotext provides a utility with the Apple version of ThinkTank to move files between Pascal and ProDOS or DOS 3.3. You need that utility for this transfer.

SYSTEM REQUIREMENTS

$\sqrt{\text{IBM}^{(8)}}$ PC or 100% compatible:

- ThinkTank™ for the IBM
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ Apple[®] II computer:

- ThinkTank for the Apple IITranslate utility from Living Videotext
- ProDOSTM System Master
- · STRIPPER for the Apple II
- Epson RX or FX; or ImageWriter™ I or II
- Dumpling[™], Grappler[™], or Super Serial Card™ (built into Apple //c)

√ Cauzin Softstrip[®] Reader:

- IBM PC Accessory Kit
- Apple II Accessory Kit

To: Apple ThinkTank From: IBM

√ Save a ThinkTank outline as text

Use the Port command

- Select Textfile, Send, and Structured
 A .TXT file is written to your disk
- ✓ Convert the .TXT file to Apple format depending on your Apple ThinkTank
 Run IBM2PDOS for ProDOS
 Run BLUE2RED for DOS 3.3

- √ Print strips of the converted .TXT file with IBM STRIPPER
- √ Read strips into Apple II Press P for ProDOS or D for DOS 3.3 depending on your ThinkTank.
- √ Move the text file to Pascal Use the Translate utility that Living Videotext bundles with Think Tank.
- $\sqrt{\text{Load the text file into ThinkTank}}$
 - Use the Port commandSelect Textfile and Receive

To: IBM ThinkTank From: Apple II


 $\sqrt{ ext{Save a ThinkTank outline as text}}$

Use the Port command

- Select Textfile, Send, and Structured
 A .TEXT file is written to your data disk
- $\sqrt{\text{Convert the .TEXT file to DOS 3.3}}$
 - Use the ThinkTank Translate utility to
 - Use your ProDOS System Master to convert the file to DOS 3.3
- $\sqrt{\text{Print strips of the DOS 3.3 text file}}$ with Apple STRIPPER
- $\sqrt{\text{Read strips into IBM PC}}$ Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file Add a .TXT extension to the new file.
- ✓ Load the .TXT file into ThinkTank
 Use the Port command
 Select Textfile and Receive
 Select Word-wrapped and Standard

Between APPLE II THINKTANK and MACINTOSH THINKTANK

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging outline files between ThinkTank on a Macintosh and ThinkTank on an Apple II computer.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Living Videotext provides a utility with the Apple version of ThinkTank to move files between Pascal and ProDOS or DOS 3.3. You need that utility for this transfer.

SYSTEM REQUIREMENTS

√ Macintosh[™] computer:

- ThinkTankTM for the Macintosh
- STRIPPER™ for the Macintosh
- ImageWriter™ I or II

√ Apple® II computer:

- ThinkTank for the Apple IITranslate utility from Living Videotext
- ProDOS™ System Master
- STRIPPER for the Apple II • Epson® RX or FX; or ImageWriter I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- Apple II Accessory Kit

To: Apple ThinkTank From: Macintosh

- Create a ThinkTank outline Select Save from the File menu.
- $\sqrt{ ext{Print}}$ strips of the outline file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- $\sqrt{\text{Read strips into Apple II}}$ Press P for ProDOS or D for DOS 3.3 depending on your ThinkTank utility.
- **√** Move the text file to Pascal Use the Translate utility that Living Videotext bundled with ThinkTank.
- Load the text file into ThinkTank
 - Use the Port command
 - Select Textfile and Receive


To: Mac ThinkTank From: Apple II

- $\sqrt{}$ Save a ThinkTank outline as text
 - Use the Port command

 - Select Textfile, Send, and StructuredA .TEXT file is written to your disk
- $\sqrt{\text{Convert the .TEXT file to DOS 3.3}}$
 - Use the ThinkTank Translate utility to move the file from Pascal to ProDOS
 - Use your ProDOS System Master to convert the file to DOS 3.3
- $\sqrt{\text{Print strips of the DOS 3.3 text}}$ file with Apple STRIPPER
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Run CONVERT on the file This converts a file to Macintosh format.
- $\sqrt{ ext{Load}}$ the text file into ThinkTank Select Open from the File menu.

APPLEWORKS to WORD WORD to APPLEWORKS

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between AppleWorks on an Apple II and Microsoft Word on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but an IBM file uses straight ASCII. Also, IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return.

SYSTEM REQUIREMENTS

√ Apple[®] II computer:

• AppleWorksTM

ProDOS™ System Master
 STRIPPER™ for the Apple II

Epson[®] RX or FX; or ImageWriter[™] I or II

 DumplingTM, GrapplerTM, or Super Serial CardTM (built into Apple //c)

√ IBM® PC or 100% compatible:

• Microsoft® Word

· STRIPPER for the IBM

· Epson RX or FX printer

· Printer interface card

√ Cauzin Softstrip® Reader:

· Apple II Accessory Kit

• IBM PC Accessory Kit

To: AppleWorks From: Word

- $\sqrt{}$ Save a Word document as ASCII
 - Choose the Transfer Save command
 - · Add a .TXT extension to the filename
 - Choose No Formatting
- $\sqrt{\text{Run BLUE2RED}}$ on the .TXT file This converts a file to Apple format.
- √ Print strips of the converted .TXT file with IBM STRIPPER Check printer ribbon and paper supply.
- √ Read strips into Apple II


 Press P for the ProDOS version of the Cauzin communications program.
- √ Load into AppleWorks
 Open a Word Processing file from the text (ASCII) file.

To: Word From: AppleWorks

- √ For a word processing file Print to a text (ASCII) file on disk.
- √ For a spreadsheet or data base
 - Open-Apple-P
 - Open-Appie-r
 Select data, set format as prompted
 Open-Apple-P, Print to the Clipboard
 Open Word Processing file from Scratch
 Open-Apple-M, Move from Clipboard
 Edit the text if necessary
 Print to a text (ASCII) file on disk
- $\sqrt{\text{Convert the text file to DOS 3.3}}$ Use your ProDOS System Master.
- √Print strips of the text file with Apple STRIPPER
- √ Read strips into IBM PC Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- $\sqrt{
 m Open}$ the converted file from Word Use the Transfer Load command.

APPLE WRITER toWORD WORD to APPLE WRITER

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between Apple Writer on an Apple II and Microsoft Word on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but an IBM file uses straight ASCII. Also, IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return.

SYSTEM REQUIREMENTS

√ Apple[®] II computer:

• Apple WriterTM

ProDOS™ System Master

STRIPPER™ for the Apple II
 Epson® RX or FX; or ImageWriter™ I or II

 Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ IBM® PC or 100% compatible:

• Microsoft® Word

• STRIPPER for the IBM

· Epson RX or FX printer

· Printer interface card

√ Cauzin Softstrip® Reader:

Apple II Accessory KitIBM PC Accessory Kit

To: Apple Writer

From: Word

$\sqrt{ m Save}$ a Word document as ASCII

- · Choose the Transfer Save command
- · Add a .TXT extension to the filename
- Choose No Formatting
- √ Run BLUE2RED on the .TXT file This converts a file to Apple format.
- √ Print strips of the converted .TXT file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Apple II

 Press D for DOS 3.3 or P for ProDOS depending on your Apple Writer.
- √ Load into Apple Writer


To: Word

From: Apple Writer

- √ For ProDOS Apple Writer
 Use your ProDOS System Master to convert your file to DOS 3.3.
- √ For DOS 3.3 Apple Writer Save file as usual.
- $\sqrt{\text{Print strips of the text file with Apple STRIPPER}}$
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- $\sqrt{\text{Run RED2BLUE}}$ on the file
- √ Open the converted file from Word Use the Transfer Load command.

WORD to MacWRITE MacWRITE to WORD

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between Microsoft Word on an IBM PC or 100% compatible and MacWrite on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. IBM text files use a carriage return and line feed at the end of each line, while Macintosh uses just carriage returns.

SYSTEM REQUIREMENTS

√ Macintosh™ computer:

- MacWriteTM
- STRIPPER™ for the Macintosh
- ImageWriter™ I or II

√ IBM® PC or 100% compatible:

- Microsoft® Word
- STRIPPER for the IBM
- Epson® RX or FX printer
- Printer Interface Card

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- · Apple II Accessory Kit

To: MacWrite From: Word

√ Save a Word document as ASCII

- Choose the Transfer Save command
- Add a .TXT extension to the filename
- Choose No Formatting
- √ Run IBM2MAC on the .TXT file
 This converts a file to Macintosh format.
- √ Print strips of the converted .TXT file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Load into MacWrite
 Let carriage returns mark Paragraphs.


To: Word From: MacWrite

- √ Create a text file with MacWrite
 - · Save the file as Text Only
 - · Let carriage returns mark Paragraphs
- √ Print strips of the text file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- √ Open the converted file from Word Use the Transfer Load command.

SPREADSHEET TRANSFER

LOTUS 1-2-3 to EXCEL EXCEL to LOTUS 1-2-3

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging WKS files between Lotus 1-2-3 on an IBM PC or 100% compatible and Excel on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

This procedure transfers a complete worksheet between these two applications. Both formulas and data are transferred. Consult the Appendix for Lotus users in the Excel manual.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- Lotus 1-2-3®
- STRIPPER TM for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ Macintosh[™] computer:

- ExcelTM
- STRIPPER for the Macintosh
- ImageWriter™ I or II

- IBM PC Accessory Kit
- Macintosh Accessory Kit (CauzComm 1.6 or higher)

To: Excel

From: Lotus 1-2-3

- √ Create a .WKS file with Lotus Select Save from the File menu.
- √ Print strips of the .WKS file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select None from File Conversion
- √ Open the file from Excel
 - Select Open from the File menu
 - Select filename
 - · Click on the Open button

To: Lotus 1-2-3

From: Excel

√ Create a .WKS file with Excel

- Select Save As from the File menu
- · Click on WKS
- Click on Save

√ Print strips of the .WKS file with Macintosh STRIPPER

- Select File Conversion from Configure
- Select Text from File Conversion

√ Read strips into IBM PC


Filenames are automatically edited to match IBM requirements.

√ Open the file from Lotus 1-2-3
Select Retrieve from the File menu.

SPREADSHEET TRANSFER

LOTUS 1-2-3 to APPLEWORKS APPLEWORKS to LOTUS 1-2-3

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between Lotus 1-2-3 on an IBM PC or 100% compatible and AppleWorks on an Apple II.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that Lotus saves number with double-precision, but AppleWorks uses single-precision. Also, file formats are different on the two machines. Utilities are enclosed to solve these problems.

This procedure transfers figures between these two applications. Formulas are not transferred.

SYSTEM REQUIREMENTS

√ Apple® II computer:

- AppleWorksTM
- ProDOSTM System Master
- · STRIPPER™ for the Apple II
- Epson® RX or FX; or ImageWriter™ I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ IBM® PC or 100% compatible:

- Lotus 1-2-3®
- · STRIPPER for the IBM PC
- · Epson RX or FX printer
- · Printer interface card

- IBM PC Accessory Kit
- · Apple II Accessory Kit

To: AppleWorks

From: Lotus 1-2-3

- V Create a DIF file of your Lotus WKS file
 - Select the Translate utility of Lotus
 - Choose FROM Lotus TO DIF
 - A .DIF file is written to your disk from your .WKS file
- $\sqrt{\text{Run BLUE2RED}}$ on the .DIF file This converts a file to Apple II format.
- $\sqrt{\text{Print strips of the converted .DIF file with}}$ IBM STRIPPER Check printer ribbon and paper supply.
- √ Read strips into Apple II Press P for ProDOS.
- √ Run DIF.FIXER on the DIF file This changes the numbers from double precision to single.
- √ Load into AppleWorks Follow the manual for creating a spreadsheet from a DIF file.

To: Lotus 1-2-3 From: AppleWorks

- $\sqrt{}$ Save the AppleWorks data as a DIF file
 - Press Open-Apple-P and select data
 Print to a DIF file on disk


 - DIF order is Columns
- √ Convert the DIF file to DOS 3.3 Use your ProDOS System Master to convert your file to DOS 3.3.
- √ Print strips of the DIF file with Apple STRIPPER
- √ Read strips into IBM PC Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file Add the extension .DIF to the new file.
- √ Convert the .DIF file to Lotus 1-2-3
 - Select the Translate utility of LotusChoose FROM DIF TO Lotus

 - · A .WKS file is written to your disk

DATA BASE TRANSFER

APPLEWORKS to dBASE dBASE to APPLEWORKS

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging text files between AppleWorks on an Apple II and dBASE on an IBM PC or 100% compatible.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

A problem with this particular transfer is that all text files are not alike. Apple DOS 3.3 files set the high bit for all characters, but an IBM file uses straight ASCII. Also, IBM files use a carriage return and a line feed to end each line, while Apple uses just a carriage return.

SYSTEM REQUIREMENTS

√ Apple[®] II computer:

AppleWorksTM

ProDOS™ System Master

• STRIPPER™ for the Apple II

• Epson® RX or FX; or ImageWriter™ I or II

 Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ IBM® PC or 100% compatible:

· dBASE®

· STRIPPER for the IBM

• Epson RX or FX printer

· Printer interface card

√ Cauzin Softstrip® Reader:

· Apple II Accessory Kit

• IBM PC Accessory Kit

To: AppleWorks From: dBASE

- √ Create a file with dBASE
 - Use the COPY TO command
 - Specify SDF format
- √ Run DBCONVRT.BAS on the file This converts between dBASE and AppleWorks file structure.
- √ Run BLUE2RED on the file
 This converts the file to Apple format.
- √ Print strips of the file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Apple II Press P for ProDOS.
- √ Load into AppleWorks
 Follow the manual for creating or adding to a data base from a text (ASCII) file.


To: dBASE From: AppleWorks

- $\sqrt{\text{Save the data as a text (ASCII) file}}$
 - Open-Apple-P and create a Table Format
 - Adjust column widths to match the dataSend the report to a text file on disk
- Send the report to a text file on disk
- √ Convert the file to DOS 3.3
 Use your ProDOS System Master to convert your file to DOS 3.3.
- $\sqrt{\text{Print strips with Apple STRIPPER}}$
- √ Read strips into IBM PC
 Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file
- √ Run DBCONVRT.BAS on the file Enter the size of each field that DBASE is expecting.
- $\sqrt{\text{Import the file into dBASE}}$
 - Use APPEND FROM
 - · File format is SDF

SOURCE CODE TRANSFER

Between TURBO PASCAL and MACINTOSH PASCAL

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging source code text files between Turbo Pascal on an IBM PC or 100% compatible and Macintosh Pascal on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Procedures and commands (such as, graphics and windowing) supported by only one Pascal will not function on the other. However, you can develop a library of procedures for one system that mimic the reserved words of the other system.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- Turbo Pascal®
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ Macintosh™ computer:

- · Macintosh Pascal
- · STRIPPER for the Macintosh
- ImageWriter™ I or II

- IBM PC Accessory Kit
- Macintosh Accessory Kit (CauzComm 1.6 or higher)

To: Macintosh Pascal From: Turbo Pascal

- √ Create a text file with Turbo Pascal Choose Save from the main menu.
- √ Run IBM2MAC on the file
 This converts a file to Macintosh format.
- √ Print strips of the converted text file with IBM STRIPPER
 Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Open the file in Macintosh Pascal
 - Select Open from the File menu
 - · Select Go from the Run menu


To: Turbo Pascal From: Mac Pascal

- √ Create a text file with Mac Pascal Select Save As from the File menu.
- √ Print strips of the text file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into IBM PC
 Filenames are automatically edited to match IBM requirements.
- √ Run RED2BLUE on the file
 Add the .PAS extension to the new file.
- √ Open the file from Turbo Pascal
 - Open the .PAS file with Edit filename
 - Insert the .PAS file into another file with Control-K, R

SOURCE CODE TRANSFER

IBM BASIC to Applesoft BASIC Applesoft BASIC to IBM BASIC

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging source code text files between BASIC on an IBM PC or 100% compatible and Applesoft BASIC on an Apple II.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Commands supported by only one BASIC (such as graphics) will not function on the other. However, you can develop a library of subroutines for one system that will mimic the reserved words of the other system.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- BASIC or BASICA
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ Apple® II computer (any model):

- · STRIPPER for the Apple II
- Epson RX or FX; or ImageWriter™ I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

- IBM PC Accessory Kit
- · Apple II Accessory Kit

To: Applesoft BASIC From: IBM BASIC

- √ Create a text file with IBM BASIC
 - Use the A parameter of SAVE to send the program to an ASCII text file.
 - Enter SAVE "filename", A
- √ Run BLUE2RED on the file This converts the file to Apple II format.
- $\sqrt{\text{Print strips of the converted text}}$ file with IBM STRIPPER Check printer ribbon and paper supply.
- √ Read strips into Apple II Press D for DOS 3.3 or P for ProDOS.
- $\sqrt{\text{EXEC}}$ the text file into memory
 - Enter EXEC filename
 - LIST and SAVE as usual

To: IBM BASIC From: Applesoft


- √ Create a text file from Applesoft

 - LOAD a BASIC program
 EXEC TEXT.MAKER to add line 1
 - RUN the program
 - File TXT is a text file of the program
- √ Print strips with Apple STRIPPER Filename is TXT, unless you rename it.
- √ Read strips into IBM PC Filenames are automatically edited to match IBM requirements.
- √ Run RED2BLUE on the file Add the .BAS extension to the new file.
- √ Run BASIC or BASICA LOAD the program and RUN as usual.

SOURCE CODE TRANSFER

IBM BASIC to Macintosh BASIC Macintosh BASIC to IBM BASIC

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for exchanging source code text files between BASIC on an IBM PC or 100% compatible and Microsoft BASIC on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Commands supported by only one BASIC (such as windowing) will not function on the other. However, you can develop a library of subroutines for one system that will mimic the reserved words of the other system.

SYSTEM REQUIREMENTS

$\sqrt{IBM^{\otimes}}$ PC or 100% compatible:

- BASIC or BASICA
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ Macintosh™ computer (any model):

- · Microsoft® BASIC
- · STRIPPER for the Macintosh
- ImageWriter™ I or II

- IBM PC Accessory Kit
- Macintosh Accessory Kit (CauzComm 1.6 or higher)

To: Mac BASIC From: IBM BASIC

- Create a text file with IBM BASIC
 - Use the A parameter of SAVE to send the program to an ASCII text file
 • Enter SAVE "filename",A
- √ Print strips of the text file with IBM STRIPPER Check printer ribbon and paper supply.
- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Open the file in Macintosh BASIC Select Open from the File menu.

To: IBM BASIC From: Mac BASIC

- √ Create a text file from Mac BASIC
 - Be sure to use line numbers
 - · Select Save As from the File menu
 - · Click Text, click Save
- √ Print strips of the text file with Macintosh STRIPPER
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Read strips into IBM PC Filenames are edited to IBM requirements.
- √ Run RED2BLUE on the file Add the .BAS extension to the new file.
- √ Run BASIC or BASICA LOAD the program and RUN as usual.

FRAMEWORK to PAGEMAKER



This Note details the procedure for moving text files from Framework on an IBM PC or 100% compatible to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Framework to create spreadsheets, data bases, and word processing documents. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

$\sqrt{\text{IBM}^{\mathbb{R}}}$ PC or 100% compatible:

- Framework™
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ MacintoshTM computer:

PageMaker[®]

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: Framework

- Create a text file from Framework
 - · Select the frame you want to transfer
 - Press CONTROL-D for the disk menu
 - Move to EXPORT and press ENTER
 - Move to ASCII TEXT, press ENTER
 A .TXT file is written to disk
- √ Run IBM2MAC on the .TXT file This converts a file to Macintosh format.
- √ Print strips of the converted .TXT file with IBM STRIPPER Check printer ribbon and paper supply.

To: PageMaker

- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Edit the file with MacWrite (option) Since the Mac uses proportional spacing, you may need to re-align columns.
 - · Let carriage returns mark Paragraphs
 - · Edit and format the text file
- √ Open PageMaker
 - Double click the PageMaker icon
 - · Select New or Open from the File menu
- √ Place the file
 - Choose Place from the File menu
 - Select the filename

Add even more value and impact

Print Softstrip data strips of working Framework disk files on the pages of your publication. Find out how in Application Note #849-5010.

LOTUS 1-2-3 to PAGEMAKER



This Note details the procedure for moving text files from Lotus 1-2-3 on an IBM PC or 100% compatible to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Lotus 1-2-3 to create spreadsheets, financial models, and budget outlines. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

$\sqrt{IBM^{(R)}}$ PC or 100% compatible:

- Lotus 1-2-3®
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ MacintoshTM computer:

• PageMaker®

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: Lotus 1-2-3

√ Create a text file with Lotus

- · Load your worksheet into Lotus
- Press /P to print and F for file
- Enter a filename for the text file
- Set the data Range
- · Press G for Go
- Press Q to return to Lotus and close the text file
- √ Run IBM2MAC on the text file
 This converts a file to Macintosh format.
- √ Print strips of the converted text file with IBM STRIPPER Check printer ribbon and paper supply.

To: PageMaker

√ Read strips into Macintosh

- Select File Conversion from Configure
- Select Text from File Conversion

√ Edit the file with MacWrite (option) Since the Mac uses proportional spacing, you may need to re-align columns.

- · Let carriage returns mark Paragraphs
- Edit and format the text file

√ Open PageMaker

- Double click the PageMaker icon
- Select New or Open from the File menu

√ Place the file

- Choose Place from the File menu
- Select the filename

Add even more value and impact

Print Softstrip data strips of working Lotus 1-2-3 disk files on the pages of your publication. Find out how in Application Note #849-5010.

WORDSTAR to PAGEMAKER

Exchanging
Computer Data
Using Cauzin
Softstrip®
Data Strips

This Note details the procedure for moving text files from WordStar on an IBM PC or 100% compatible to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of WordStar to create word processing documents. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- WordStar[®]
- STRIPPER TM for the IBM
- · Epson® RX or FX printer
- · Printer interface card

√ Macintosh™ computer:

PageMaker[®]

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
 - IBM PC Accessory Kit

From: WordStar

- √ Create a file with WordStar Save the file as usual.
- √ Run IBM2MAC on the file
 This converts the file to Macintosh format.
- √ Print strips of the converted Word-Star file with IBM STRIPPER Check printer ribbon and paper supply.

To: PageMaker

√ Read strips into Macintosh

- Select File Conversion from Configure
- Select Text from File Conversion

√ Edit the file with MacWrite (option) Since the Mac uses proportional spacing,

you may need to re-align margins or tabs.

• Let carriage returns mark Paragraphs

• Edit and format the text file

√ Open PageMaker

- Double click the PageMaker icon
- Select New or Open from the File menu

√ Place the file


- · Choose Place from the File menu
- Select the filename

Add even more value and impact

Print Softstrip data strips of actual WordStar disk files on the pages of your publication. Find out how in Application Note #849-5010.

WORD to PAGEMAKER

Exchanging
Computer Data
Using Cauzin
Softstrip®
Data Strips



This Note details the procedure for moving text files from Microsoft Word on an IBM PC or 100% compatible to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Word to create word processing documents. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- Microsoft® Word
- STRIPPER™ for the IBM
- · Epson® RX or FX printer
- · Printer interface card

√ MacintoshTM computer:

PageMaker[®]

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: Word

Save a Word document as ASCII

- Choose the Transfer Save command
- · Add a .TXT extension to the filename
- Choose No Formatting
- √ Run IBM2MAC on the .TXT file
 This converts the file to Macintosh format.
- √ Print strips of the converted .TXT file with IBM STRIPPER
 Check printer ribbon and paper supply.

To: PageMaker

- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Edit the file with MacWrite (option)
 Since the Mac uses proportional spacing,
 you may need to re-align margins or tabs.
 - Let carriage returns mark Paragraphs
 - Edit and format the text file
- √ Open PageMaker
 - Double click the PageMaker icon
 - Select New or Open from the File menu
- √ Place the file
 - Choose Place from the File menu
 - · Select the filename

Add even more value and impact

Print Softstrip data strips of actual Word disk files on the pages of your publication. Find out how in Application Note #849-5010.

MULTIMATE to PAGEMAKER



This Note details the procedure for moving text files from MultiMate on an IBM PC or 100% compatible to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of MultiMate to create word processing documents. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

- $\sqrt{\text{IBM}^{\text{(R)}}}$ PC or 100% compatible:
 - MultiMateTM
 - STRIPPER™ for the IBM
 - · Epson® RX or FX printer
 - · Printer interface card
- √ Macintosh[™] computer:
 - PageMaker®
- √ Cauzin Softstrip® Reader:
 - Macintosh Accessory Kit (CauzComm 1.6 or higher)
 - IBM PC Accessory Kit

From: MultiMate

- create a file with MultiMate
- $\sqrt{}$ Convert MultiMate file to ASCII
 - Run FILECONV (MultiMate Utilities)
 - Select MultiMate to ASCII conversion
 - Enter filenames as prompted
 - Use .TXT extension for new filename
 - Press F10 to convert the file
- $\sqrt{\mathrm{Run}}$ IBM2MAC on the .TXT file This converts the file to Macintosh format.
- $\sqrt{}$ Print strips of the converted .TXT file with IBM STRIPPER Check printer ribbon and paper supply.

To: PageMaker

- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- $\sqrt{
 m Edit}$ the file with MacWrite (option)
 - Since the Mac uses proportional spacing, you may need to re-align margins or tabs.
 - · Let carriage returns mark Paragraphs · Edit and format the text file
- √ Open PageMaker
 - Double click the PageMaker icon
 - · Select New or Open from the File menu
- √ Place the file
 - Choose Place from the File menu
 - Select the filename

Add even more value and impact

Print Softstrip data strips of actual MultiMate disk files on the pages of your publication. Find out how in Application Note #849-5010.

APPLEWORKS to PAGEMAKER



This Note details the procedure for moving text files from AppleWorks on an Apple II to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of AppleWorks to create spreadsheets, data bases, and word processing documents. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ Apple® II computer:

AppleWorksTM

ProDOS™ System Master

 \bullet STRIPPER $^{\text{TM}}$ for the Apple II

• Epson® RX or FX; or ImageWriter™ I or II

 Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ Macintosh™ computer:

PageMaker[®]

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- Apple II Accessory Kit

From: AppleWorks

For a spreadsheet or data base

Open-Apple-P

- Select data, set format as prompted
- Open-Apple-P, Print to the Clipboard
 Open Word Processing file from Scratch
- Open-Apple-M, Move from Clipboard
- Edit the text if necessaryPrint to a text (ASCII) file on disk
- $\sqrt{\text{For a word processing file}}$ Print to a text (ASCII) file on disk.
- √ Convert the text file to DOS 3.3 Use your ProDOS System Master.
- √ Print strips of the converted text file with Apple STRIPPER.

To: PageMaker

- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Run CONVERT on the text file This converts a file to Macintosh format.
- √ Edit the file with MacWrite (option) Since the Mac uses proportional spacing, you may need to re-align columns or tabs. · Let carriage returns mark Paragraphs
- √ Open PageMaker • Double click on the PageMaker icon
 - Select New or Open from the File menu
- √ Place the file

Choose Place from File menu, select file.

Add even more value and impact

Print Softstrip data strips of AppleWorks text files on the pages of your publication. Find out how in Application Note #849-5010.

APPLE WRITER to PAGEMAKER

Exchanging
Computer Data
Using Cauzin
Softstrip®
Data Strips

This Note details the procedure for moving text files from Apple Writer on an Apple II to PageMaker on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Apple Writer to create word processing documents. Then let the Softstrip System transport your work into PageMaker publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ Apple® II computer:

- Apple WriterTM (DOS 3.3 or ProDOSTM)
- ProDOS System Master
- STRIPPERTM for the Apple II
- Epson[®] RX or FX; or ImageWriter™ I or II
- Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ MacintoshTM computer:

• PageMaker®

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- · Apple II Accessory Kit

From: Apple Writer

- √ For ProDOS Apple Writer
 Use your ProDOS System Master to convert your files to DOS 3.3
- √ For DOS 3.3 Apple Writer Save files as usual.
- ✓ Print strips of the text file with Apple STRIPPER
 Check printer ribbon and paper supply.

To: PageMaker

- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Run CONVERT on the file
 This converts a file to Macintosh format.
- √ Edit the file with MacWrite (option)
 Since the Mac uses proportional spacing,
 you may need to re-align margins or tabs.
 - · Let carriage returns mark Paragraphs
 - · Edit and format the text file
- √ Open PageMaker
 - Double click the PageMaker icon
 - Select New or Open from the File menu
- √ Place the file
 - · Choose Place from the File menu
 - · Select the filename

Add even more value and impact

Print Softstrip data strips of actual Apple Writer disk files on the pages of your publication. Find out how in Application Note #849-5010.

FRAMEWORK to READYSETGO



This Note details the procedure for moving text files from Framework on an IBM PC or 100% compatible to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Framework to create spreadsheets, data bases, and word processing documents. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- FrameworkTM
- STRIPPER™ for the IBM
- Epson[®] RX or FX printer
- · Printer interface card

√ MacintoshTM computer:

ReadySetGo™

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: Framework

Create a text file from Framework

- Select the frame you want to transfer
- Press CONTROL-D for the disk menu
- Move to EXPORT and press ENTER
 Move to ASCII TEXT, press ENTER
- · A .TXT file is written to disk
- √ Run IBM2MAC on the .TXT file This converts a file to Macintosh format.
- $\sqrt{ ext{Print strips of the converted .TXT}}$ file with IBM STRIPPER Check printer ribbon and paper supply.

To: ReadySetGo

√ Read strips into Macintosh

- Select File Conversion from Configure
- Select Text from File Conversion

√ Open ReadySetGo

- Double click the ReadySetGo icon
- Select New or Open from the File menu

√ Place the file

- Choose Get Text from the File menu
- Select the filename
- Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of working Framework disk files on the pages of your publication. Find out how in Application Note #849-5010.

LOTUS 1-2-3 to READYSETGO



This Note details the procedure for moving text files from Lotus 1-2-3 on an IBM PC or 100% compatible to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Lotus 1-2-3 to create spreadsheets, financial models, and budget outlines. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

$\sqrt{\text{IBM}^{\textcircled{R}}}$ PC or 100% compatible:

- Lotus 1-2-3®
- STRIPPERTM for the IBM
- Epson® RX or FX printer
- Printer interface card

√ Macintosh™ computer:

ReadySetGo™

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: Lotus 1-2-3

√ Create a text file with Lotus

- · Load your worksheet into Lotus
- Press /P to print and F for file
- Enter a filename for the text file
- Set the data Range
- · Press G for Go
- Press Q to return to Lotus and close the text file
- √ Run IBM2MAC on the text file
 This converts a file to Macintosh format.
- √ Print strips of the converted text file with IBM STRIPPER
 Check printer ribbon and paper supply.

To: ReadySetGo

√ Read strips into Macintosh

- Select File Conversion from Configure
- Select Text from File Conversion

√ Open ReadySetGo

- Double click the ReadySetGo icon
- Select New or Open from the File menu

$\sqrt{\text{Place the file}}$


- · Choose Get Text from the File menu
- Select the filename
- Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of working Lotus 1-2-3 disk files on the pages of your publication. Find out how in Application Note #849-5010.

WORDSTAR to READYSETGO

Exchanging
Computer Data
Using Cauzin
Softstrip®
Data Strips



This Note details the procedure for moving text files from WordStar on an IBM PC or 100% compatible to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of WordStar to create word processing documents. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ IBM® PC or 100% compatible:

- WordStar®
- STRIPPER TM for the IBM
- · Epson® RX or FX printer
- · Printer interface card

√ Macintosh[™] computer:

ReadvSetGo™

√ Cauzin Softstrip[®] Reader:

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: WordStar

- √ Create a file with WordStar Save the file as usual.
- √ Run IBM2MAC on the file
 This converts the file to Macintosh format.
- √ Print strips of the converted Word-Star file with IBM STRIPPER Check printer ribbon and paper supply.

To: ReadySetGo


- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Open ReadySetGo
 - Double click the ReadySetGo icon
 - Select New or Open from the File menu
- $\sqrt{\text{Place the file}}$
 - Choose Get Text from the File menu
 - · Select the filename
 - Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of actual WordStar disk files on the pages of your publication. Find out how in Application Note #849-5010.

WORD to READYSETGO

Exchanging Computer Data Using Cauzin Softstrip® Data Strips



This Note details the procedure for moving text files from Microsoft Word on an IBM PC or 100% compatible to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Word to create word processing documents. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ IBM[®] PC or 100% compatible: • Microsoft[®] Word

- STRIPPER™ for the IBM
- · Epson® RX or FX printer
- · Printer interface card

√ MacintoshTM computer:

ReadySetGoTM

- · Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: Word

$\sqrt{}$ Save a Word document as ASCII

- Choose the Transfer Save command
 Add a .TXT extension to the filename
- Choose No Formatting
- $\sqrt{}$ Run IBM2MAC on the .TXT file This converts the file to Macintosh format.
- $\sqrt{ ext{Print}}$ strips of the converted .TXT file with IBM STRIPPER Check printer ribbon and paper supply.

To: ReadySetGo

$\sqrt{ m Read}$ strips into Macintosh

- Select File Conversion from Configure
- Select Text from File Conversion

√ Open ReadySetGo

- Double click the ReadySetGo icon
- Select New or Open from the File menu

√ Place the file


- Choose Get Text from the File menu
- Select the filename
- Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of actual Word disk files on the pages of your publication. Find out how in Application Note #849-5010.

MULTIMATE to READYSETGO





This Note details the procedure for moving text files from MultiMate on an IBM PC or 100% compatible to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of MultiMate to create word processing documents. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

$\sqrt{\text{IBM}^{\$}}$ PC or 100% compatible:

- MultiMateTM
- STRIPPER™ for the IBM
- Epson® RX or FX printer
- · Printer interface card

√ Macintosh™ computer:

ReadySetGo™

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- IBM PC Accessory Kit

From: MultiMate

- $\sqrt{}$ Create a file with MultiMate
- $\sqrt{\text{Convert MultiMate file to ASCII}}$
 - Run FILECONV (MultiMate Utilities)
 - Select MultiMate to ASCII conversion
 - · Enter filenames as prompted
 - Use .TXT extension for new filename
 - Press F10 to convert the file
- $\sqrt{}$ Run IBM2MAC on the .TXT file This converts the file to Macintosh format.
- $\sqrt{ ext{Print strips of the converted .TXT}}$ file with IBM STRIPPER Check printer ribbon and paper supply.

To: ReadySetGo

- $\sqrt{\text{Read strips into Macintosh}}$
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Open ReadySetGo
 - Double click the ReadySetGo icon
 - Select New or Open from the File menu
- **V** Place the file
 - Choose Get Text from the File menu
 - Select the filename
 - Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of actual MultiMate disk files on the pages of your publication. Find out how in Application Note #849-5010.

DESKTOP PUBLISHING

APPLEWORKS to READYSETGO



This Note details the procedure for moving text files from AppleWorks on an Apple II to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of AppleWorks to create spreadsheets, data bases, and word processing documents. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ Apple® II computer:

AppleWorks™

ProDOS™ System Master

 \bullet STRIPPER $^{\text{TM}}$ for the Apple II

• Epson® RX or FX; or ImageWriter™ I or II

 Dumpling[™], Grappler[™], or Super Serial Card[™] (built into Apple //c)

√ Macintosh™ computer:

ReadySetGo™

√ Cauzin Softstrip® Reader:

- Macintosh Accessory Kit (CauzComm 1.6 or higher)
- Apple II Accessory Kit

From: AppleWorks

√ For a spreadsheet or data base

Open-Apple-P

Select data, set format as prompted

- · Open-Apple-P, Print to the Clipboard
- Open Word Processing file from Scratch
 Open-Apple-M, Move from Clipboard
- Edit the text if necessary
- Print to a text (ASCII) file on disk
- $\sqrt{}$ For a word processing file Print to a text (ASCII) file on disk.
- $\sqrt{\text{Convert the text file to DOS 3.3}}$ Use your ProDOS System Master.
- $\sqrt{
 m Print}$ strips of the converted text file with Apple STRIPPER.

To: ReadySetGo

$\sqrt{ m Read}$ strips into Macintosh

- Select File Conversion from Configure
- Select Text from File Conversion

$\sqrt{ m Run}$ CONVERT on the text file This converts a file to Macintosh format.

- √ Open ReadySetGo
 - Double click on the ReadySetGo icon
 - Select New or Open from the File menu

√ Place the file

- Choose Get Text from File menu
- Select the filename
- Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of AppleWorks text files on the pages of your publication. Find out how in Application Note #849-5010.

DESKTOP PUBLISHING

APPLE WRITER to READYSETGO



This Note details the procedure for moving text files from Apple Writer on an Apple II over to ReadySetGo on a Macintosh.

At the heart of the procedure is the Softstrip System. This technology allows data printed by one computer to be read into another. Anything you store on a disk, you can print on paper.

Use the power and ease of Apple Writer to create word processing documents. Then let the Softstrip System transport your work into ReadySetGo publications, ready for layout and laser printing.

SYSTEM REQUIREMENTS

√ Apple[®] II computer:

- Apple WriterTM (DOS 3.3 or ProDOSTM)
- ProDOS System Master
- STRIPPER™ for the Apple II
- Epson® RX or FX; or ImageWriter™ I or II
- DumplingTM, GrapplerTM, or Super Serial CardTM (built into Apple //c)
- √ Macintosh™ computer:
 - ReadySetGo™
- √ Cauzin Softstrip® Reader:
 - Macintosh Accessory Kit (CauzComm 1.6 or higher)
 - Apple II Accessory Kit

From: Apple Writer

- √ For ProDOS Apple Writer
 Use your ProDOS System Master to convert your files to DOS 3.3.
- √ For DOS 3.3 Apple Writer Save files as usual.
- √ Print strips of the text file with Apple STRIPPER
 Check printer ribbon and paper supply.

To: ReadySetGo

- √ Read strips into Macintosh
 - Select File Conversion from Configure
 - Select Text from File Conversion
- √ Run CONVERT on the file
 This converts a file to Macintosh format.
- √ Open ReadySetGo
 - Double click the ReadySetGo icon
 - Select New or Open from the File menu
- √ Place the file
 - · Choose Get Text from the File menu
 - · Select the filename
 - Since the Mac uses proportional spacing, you may need to realign columns or tabs

Add even more value and impact

Print Softstrip data strips of actual Apple Writer disk files on the pages of your publication. Find out how in Application Note #849-5010.

The Cauzin Converters

All files are not created equal. Some define the end of a line with a carriage return (Apple II and Macintosh). Others use both a carriage return and a line feed (IBM PC). The data strips on the next pages contain all the utilities used in this manual to make files more compatible.

Macintosh Utilities

CONVERT

- -Goes from IBM and Apple II to Macintosh
- -Removes line feed after carriage returns
- -Turns off high bits

IBM PC Utilities

BLUE2RED.COM

- -Goes from IBM to Apple DOS 3.3
- -Removes line feed after carriage returns
- -Sets all the high bits

CIPHER.BAS (requires BASIC)

-Encodes data in IBM files

DBCONVRT.BAS (requires BASIC)

-Converts between dBASE and AppleWorks

IBM2MAC.COM

- -Goes from IBM to Macintosh
- -Removes line feed after carriage returns

IBM2PDOS.COM

- -Goes from IBM to Apple ProDOS
- -Removes line feed after carriage returns

RED2BLUE.COM

- -From MAC and Apple DOS 3.3 to IBM
- -Adds line feed after carriage returns
- -Turns off all the high bits

Apple II Utilities

DIF.FIXER

- -Command is RUN DIF.FIXER
- -Changes a Lotus DIF file to the form Appleworks expects.

TEXT.MAKER

- -Command is EXEC TEXT.MAKER
- -Stores an Applesoft program as a text file

Lotus and Excel

IRACALC.WKS


-Working spreadsheet compatible with Lotus on a IBM and Excel on a Macintosh.



Cauzin Converters for the IBM PC 2

Cauzin Converters for the Apple II







Cauzin's SOFTSTRIP® Sy

The Perfect Complement To Your Pers Computer

The SOFTSTRIP System let's you create, pr save your computer files as "data strips" on or paper using dot matrix and laser printers. strips, you can store files conveniently and data from one type of computer to another!

Move Data Files between IBM PC's, M and Apple's:

Just follow the simple instructions in this No complicated programs to use. No messy call adapters.

For instance, print IBM PC Lotus 1-2-3 files as read them with a SOFTSTRIP reader into you Macintosh, and your ready to use the file in Or, go PC WordStar or Framework to MacW ReadySetGo, or PageMaker. Go AppleWorks Writer to dBASE or WordStar. Or visa versa. Pl more transfers, as listed in this manual.

You can even copy strips on a photocopier a distribute them between cities, states, and co

Create Computer File Copies You Copies You Copies Find Later:

End the filing of your printed letters and re separately from your computer readable copy Print your files as both text and as strips, f together, and you'll have the computer read always attached to the original text.

With the SOFTSTRIP System, anything you on disk you can print, save, and use as dat

A SYSTEM ENDORED BY THE EXP

"The SOFTSTRIP System...the best reason stop fighting paper and number it among ϵ means of data communications."

Jeff Duntemann, PC Tech

"SOFTSTRIP is a technology with as much po for changing our society as the Xerox copie floppy disk." Adam B. Green, INF

System Requirements: To use the SOFTSTRIP Systeneed is the SOFTSTRIP reader plus: Accessory Kits of the cables and software you need to read data stricomputer, and STRIPPER™ software for the comparinters you'll be using.

CAUZIN SYSTEMS, INC. 835 SOUTH MAIN STREET WATERBURY, CT 06706